

Stretch GazeBot

Control a Hello Robot Stretch 3 with your head, using Xreal One Pro AR glasses.

Project folder	~/lab/life_home/xreal_head_control
Robot	Hello Robot Stretch 3
AR glasses	Xreal One Pro (USB-C, ethernet over USB)
PC OS	Linux (tested on Ubuntu 22.04)
Robot OS	Ubuntu 22.04 + ROS 2 Humble
Author / Owner	het@operationautopilot.com
Document version	Apr 2026

1. What this project does

Stretch GazeBot is a teleoperation bridge. You wear Xreal One Pro AR glasses on your PC. The glasses stream their IMU (gyroscope + accelerometer) data over a USB-C ethernet link to your PC. A Python program on the PC reads that stream, computes head pitch / yaw / roll, and forwards pan / tilt commands to a relay program running on the Stretch 3 robot. The relay translates those into ROS 2 joint commands for the robot's head. The result: turn your head, and the robot's head turns the same way (near real-time, < 10 ms IMU latency).

There is also a DRIVE mode, where holding SPACE makes the robot's mobile base move based on head tilt (pitch → forward / reverse, yaw → turn).

System architecture

```
[Xreal One Pro glasses]
| USB-C ethernet (TCP 169.254.2.1:52998)
v
[Your PC] stretch_head_control.py
| TCP JSON commands (port 9090)
v
[Stretch 3] stretch_relay.py --> ROS 2 follow_joint_trajectory action
--> joint_head_pan / joint_head_tilt
```

Repository layout

File	Where it runs	Purpose
stretch_head_control.py	Your PC	Main bridge. Reads glasses IMU, computes head pose, sends TCP commands.
stretch_relay.py	Stretch 3	ROS 2 node. Receives TCP commands and moves head pan / tilt.
imu_server.py / imu_viz.html	Your PC	Optional: 3D visualizer in browser to verify glasses work.
src/imu_reader_fixed.py	Your PC	Reads raw IMU stream from glasses over TCP.
src/head_tracker.py	Your PC	Sensor fusion: raw IMU → calibrated pitch / yaw / roll.
src/imu_data.py	Your PC	Dataclass holding a single IMU sample.
start.sh	Your PC	Convenience launcher — pings glasses, then runs the bridge.

requirements.txt	Your PC	Python deps: numpy, pygame, PyOpenGL (visualizer only).
------------------	---------	---

2. Hardware checklist

- **Xreal One Pro** AR glasses (the regular One has not been tested and may not work).
- **USB-C cable** (data + power capable). The glasses expose a USB ethernet adapter.
- **Hello Robot Stretch 3** on the same Wi-Fi or LAN as your PC.
- **Linux PC** with Python 3.7+ (Ubuntu 22.04 recommended).
- **Network reachability**: your PC must be able to reach the robot at 172.22.243.8. If your robot has a different IP, write it down — you will need to update STRETCH_IP in `stretch_head_control.py` (line 35).

3. Initial PC setup (one-time)

3.1 Clone the repo

```
mkdir -p ~/lab/life_home && cd ~/lab/life_home
git clone <your-fork-url> xreal_head_control
cd xreal_head_control
```

If you received this code as a tarball/zip instead, extract it to `~/lab/life_home/xreal_head_control` so the relative paths in the helper scripts continue to work.

3.2 Install Python dependencies

```
# (Optional but recommended) virtualenv
python3 -m venv .venv && source .venv/bin/activate

pip install -r requirements.txt
```

Note: numpy is the only hard requirement for the head-control bridge. pygame and PyOpenGL are only needed for the optional 3D visualizer.

3.3 Plug in the glasses and verify the link

- Connect the Xreal One Pro to your PC with USB-C.
- On the glasses, open *Settings* → *Developer Menu* → *Enable Ethernet* (only needed once).
- On your PC, confirm the link:

```
ping 169.254.2.1
```

You should see replies. If not, try a different USB-C port, re-toggle ethernet in the developer menu, or check `ip addr` for an interface with a 169.254.x.x address.

3.4 (Optional) Test the glasses on their own

```
cd ~/lab/life_home/xreal_head_control
python3 imu_server.py # in one terminal
xdg-open imu_viz.html # opens a 3D cube in your browser
```

Move the glasses — the cube should follow. Press Ctrl+C in the terminal to stop.

4. Robot setup (Stretch 3)

4.1 SSH into the robot

```
ssh hello-robot@172.22.243.8
# password: <ask lab admin>
```

Substitute your robot's IP if different. Get the robot's password from your lab admin and change it for production use.

4.2 Copy the relay script onto the robot

From your PC, copy `stretch_relay.py` into the robot's ROS 2 workspace:

```
scp ~/lab/life_home/xreal_head_control/stretch_relay.py \
hello-robot@172.22.243.8:~/het_ros2_ws/stretch_relay.py
```

(Create the directory on the robot first if needed: `mkdir -p ~/het_ros2_ws`.)

4.3 Start the Stretch driver (terminal A on the robot)

```
ssh hello-robot@172.22.243.8
conda deactivate # IMPORTANT – rclpy lives in the system Python
ros2 launch stretch_core stretch_driver.launch.py
```

Wait for the driver to finish initializing (you should see joint state messages).

4.4 Start the relay (terminal B on the robot)

```
ssh hello-robot@172.22.243.8
conda deactivate

# Confirm the action server name the driver advertises:
ros2 action list
# Look for: /stretch_controller/follow_joint_trajectory

# If your action server name differs, edit ~/het_ros2_ws/stretch_relay.py
# (see the import of hello_helpers.hello_misc – move_to_pose uses the standard
# Stretch action server, so usually no edit is needed).

python3 ~/het_ros2_ws/stretch_relay.py
```

When you see `Waiting for connection on port 9090...`, the robot side is ready.

5. Running the bridge on your PC

```
cd ~/lab/life_home/xreal_head_control
python3 stretch_head_control.py
# (or)
./start.sh # also pings the glasses first
```

First-run procedure:

- Place the glasses on a flat surface and keep them **completely still** for ~0.5 s while gyro calibration runs (you'll see a percentage).
- When you see *Calibration complete*, put the glasses on.
- Press **T** to set your current head pose as 'center'.
- Move your head left / right → robot pans. Tilt up / down → robot tilts.

5.1 Keyboard controls

Key	Mode	Action
M	Both	Toggle LOOK ↔ DRIVE mode
Space	DRIVE	Hold to enable base motion (head steers)
T	Both	Zero view — set current head pose as neutral
R	Both	Recalibrate gyroscope (keep glasses still)
L	Both	Lock / unlock — pause sending commands
Q	Both	Quit cleanly

6. Tuning sensitivity and direction

All tunables live near the top of `stretch_head_control.py`:

```
STRETCH_IP = "172.22.243.8" # robot IP
RELAY_PORT = 9090

HEAD_PAN_MIN = -3.9 # robot joint limits (rad)
HEAD_PAN_MAX = 1.5
HEAD_TILT_MIN = -1.53
HEAD_TILT_MAX = 0.79

HEAD_PAN_SCALE = 0.025 # bigger = more sensitive left/right
HEAD_TILT_SCALE = 0.015 # bigger = more sensitive up/down

COMMAND_INTERVAL = 0.05 # seconds between commands (20 Hz)

BASE_LINEAR_MAX = 0.3 # m/s – max forward/reverse in DRIVE
BASE_ANGULAR_MAX = 0.5 # rad/s – max rotation in DRIVE
BASE_DEADZONE = 5.0 # deg – no motion within this range
BASE_MAX_ANGLE = 30.0 # deg – angle that maps to full speed
```

If pan or tilt moves the wrong way, flip the sign in the assignment near `stretch_head_control.py` lines 163–164:

```
pan_rad = -yaw * HEAD_PAN_SCALE # flip sign of yaw
tilt_rad = -pitch * HEAD_TILT_SCALE # flip sign of pitch
```

7. Troubleshooting

Symptom	Most likely cause / fix
Cannot ping 169.254.2.1	Ethernet not enabled in glasses developer menu, or USB-C cable is power-only. Try a different cable.
“Connection refused” when starting the robot	<code>stretch_bridge.py</code> is not running on the robot. Start it first.
“Trajectory server not found” on the robot	<code>stretch_driver.launch.py</code> is not running, or its action server name doesn't match. Run <code>`ros2 action list`</code> on the robot to see what's running.
“No module named rclpy” on the robot	Conda is active and shadowing the system Python. Run <code>`conda deactivate`</code> first.
Robot head moves the wrong direction	Flip the sign on <code>stretch_head_control.py</code> line 163 or 164.
Tracking drifts after a minute	Press R to recalibrate (keep glasses still). Drift is inherent to gyro-only tracking — short sessions are best.
Too sensitive / not sensitive enough	Adjust <code>HEAD_PAN_SCALE</code> and <code>HEAD_TILT_SCALE</code> .
“T / R / Q does nothing”	Make sure the bridge terminal is focused. Some terminals require a single keypress (<code>cbreak</code>).

8. Optional extras (used during development)

8.1 Mount the robot's ROS workspace over SSHFS

Useful for editing files on the robot from your PC:

```
mkdir -p ~/lab/life_home/shared_folder_btw_stretch3_mypc/het_ros2_ws
sshfs hello-robot@172.22.243.8:/home/hello-robot/het_ros2_ws \
~/lab/life_home/shared_folder_btw_stretch3_mypc/het_ros2_ws
```

8.2 Robot reset / homing

```
# On the robot, before starting the driver:
stretch_free_robot_process.py # release any stuck driver locks
stretch_robot_home.py # home all joints
```

8.3 Camera streams the robot exposes

```
# (each in its own SSH terminal, after `conda deactivate`)
ros2 launch stretch_core d435i_high_resolution.launch.py # head RGB-D
ros2 launch stretch_core d405_basic.launch.py # gripper cam
ros2 run v4l2_camera v4l2_camera_node \
--ros-args -p video_device:="/dev/video6" \
-r image_raw:=/arducam/image_raw # arducam
ros2 run web_video_server web_video_server # browser viewer
ros2 launch ~/het_ros2_ws/stretch_dual_camera.launch.py # combined dual cam
```

Open the dual-camera HTML viewer on your PC:

```
google-chrome --kiosk \
file:///home/het/lab/life_home/shared_folder_btw_stretch3_mypc/het_ros2_ws/dual_camera_
view.html
```

9. How the code works (for the curious)

- **IMU stream:** `src/imu_reader_fixed.py` opens a TCP connection to `169.254.2.1:52998` and decodes binary IMU frames (~1000 Hz).
- **Sensor fusion:** `src/head_tracker.py` calibrates the gyro bias from the first ~500 samples while you hold still, then integrates gyro and fuses with accelerometer using a complementary filter (96% gyro / 4% accel).
- **Mapping:** Yaw → robot pan, pitch → robot tilt, both scaled and clamped to the Stretch joint limits.
- **Transport:** Newline-delimited JSON over a single TCP socket (port 9090).
- **Robot side:** `stretch_relay.py` is a `hello_helpers.HelloNode` ROS 2 node. It calls `move_to_pose({'joint_head_pan': pan, 'joint_head_tilt': tilt}, blocking=False)` at 20 Hz.
- **DRIVE mode:** When SPACE is held, head pitch / yaw map to base linear / angular velocities with a deadzone, sent as the same JSON shape (`{linear, angular}`).

10. Safety notes

- Always keep one hand near the Stretch e-stop while teleoperating.
- Press **L** to lock tracking before adjusting the glasses on your face.
- In DRIVE mode, releasing SPACE for ~0.2 s sends a stop command automatically.

- If the network drops, the relay simply stops getting commands; the robot will hold its last commanded pose. Press the e-stop if you need it to halt immediately.

11. Quick reference (cheat sheet)

```
# 1. Robot, terminal A:
ssh hello-robot@172.22.243.8 'conda deactivate; \
ros2 launch stretch_core stretch_driver.launch.py'

# 2. Robot, terminal B:
ssh hello-robot@172.22.243.8 'conda deactivate; \
python3 ~/het_ros2_ws/stretch_relay.py'

# 3. PC:
cd ~/lab/life_home/xreal_head_control && python3 stretch_head_control.py
```

Built from HOW_TO_USE.txt and the project source. Credits: One Pro IMU Retriever Demo by Daniel Sami Mitwalli; Stretch integration by het@operationautopilot.com.